Aumento de memoria a capturadores

- **Dirección a editar: nano /usr/local/gts_vars.env**

```
root@capturadores:/usr/local# ls -oh
total 64K
drwxr-xr-x 9 root 4.0K Apr 11  2019 apache-tomcat-8.5.20
drwxr-xr-x 2 root 4.0K Apr 20  2016 bin
-rw-r--r-- 1 root  118 Feb 27  2020 credenciales.php
-rw-r--r-- 1 root 1.7K Feb 27  2020 cron_api_vyr.php
drwxr-xr-x 2 root 4.0K Apr 20  2016 etc
-rw-r--r-- 1 root 5.2K Feb 27  2020 funciones_vyr.php
drwxr-xr-x 2 root 4.0K Apr 20  2016 games
lrwxrwxrwx 1 root   18 Apr 11  2019 gts -> /usr/local/gts_vyr
-rw-r--r-- 1 root 2.2K Sep 19  2019 gts_vars.env
drwxr-xr-x 8 root 4.0K Dec 17 12:34 gts_vyr
drwxr-xr-x 2 root 4.0K Apr 20  2016 include
lrwxrwxrwx 1 root   33 Apr 11  2019 java -> /usr/lib/jvm/java-8-openjdk-amd64
drwxr-xr-x 4 root 4.0K Apr 11  2019 lib
lrwxrwxrwx 1 root    9 Dec 16  2016 man -> share/man
drwxr-xr-x 2 root 4.0K Apr 20  2016 sbin
drwxr-xr-x 7 root 4.0K Apr 11  2019 share
drwxr-xr-x 2 root 4.0K Apr 20  2016 src
lrwxrwxrwx 1 root   31 Apr 11  2019 tomcat -> /usr/local/apache-tomcat-8.5.20
-rw-r--r-- 1 root  120 Apr 11  2019 VYR_VAR.sh
```

- **Editamos en la sección “export JAVA_MEMORY=” a la cantidad requerida**

```
  GNU nano 2.5.3                                          File: gts_vars.env

# ------------------------------------------------------------------
# File : /usr/local/gts_vars.env
# Desc : Set up GTS environment variables
# Note : This file should be read-only and owned by root
# Usage: Source within a Bash shell:
#          .  /usr/local/gts_vars.env
# ------------------------------------------------------------------

# --- Users
GTS_USER=root
TOMCAT_USER=root

# --- Directories
export GTS_HOME=`(cd -P /usr/local/gts; /bin/pwd)`
export JAVA_HOME=`(cd -P /usr/local/java; /bin/pwd)`
export JRE_HOME=${JAVA_HOME}
export CATALINA_HOME=`(cd -P /usr/local/tomcat; /bin/pwd)`
export CATALINA_BASE=${CATALINA_HOME}


# --- May be required for Java/Tomcat on systems with limited memory
export JAVA_MEMORY=1024m
#export JAVA_OPTS=-Xmx256m
#export ANT_OPTS=-Xmx100m
#export CATALINA_OPTS=-Xmx512m


^G Get Help    ^O Write Out   ^W Where Is    ^K Cut Text    ^J Justify     ^C
^X Exit        ^R Read File   ^\ Replace     ^U Uncut Text  ^T To Spell    ^_
```

- **Guardas y salir, reiniciamos capturadores con el comando “service vyrgts restart”**

```
root@capturadores:/usr/local# service vyrgts restart
```

- **VERIFICAR EL AUMENTO/DISMINUCION DE LA MEMORIA HACIA LOS CAPTURADORES comando “htop”**



From:
https://wiki.vyrglobalservices.com/ - **Wiki V & R GLOBAL SERVICES S.A.C**

Permanent link:
https://wiki.vyrglobalservices.com/doku.php?id=wiki:memoria_cap

Last update: **2022/09/13 14:09**